

# MainConcept 2GO OTT File Transcoder DASH

## User Guide

### Contents

1. Introduction.....	2
2. Installation.....	2
2.1 Installing Docker.....	2
2.2 Resources for Docker.....	3
2.3 Installing MainConcept 2GO.....	3
3. Settings.....	4
3.1 Supported Input Codecs & Formats.....	4
3.2 Supported Output Formats.....	4
4. Configuration.....	4
4.1 Configuring shared folders.....	4
4.2 Preset Usage.....	5
5. Usage.....	7
5.1 Starting MainConcept 2GO.....	7
5.2 Using job description file.....	7
5.3 Using properties file.....	9
5.5 Stopping MainConcept 2GO execution.....	12
6. Technical Support.....	12
7. Credits.....	13

## 1. Introduction

The MainConcept 2GO OTT File Transcoder DASH is an optimized Docker container for transcoding file-based media archives into adaptive streaming format MPEG-DASH as AVC/H.264 and HEVC/H.265 for playback on iOS and Android devices. The included packager creates ready-to-use manifest and playlist files that are ready for uploading to a CDN (Akamai & CloudFront) or HTTP servers.

### Features:

- Adaptive Bitrate Stream Encoding to MPEG-DASH up to 4K 8-bit and 10-bit
- MPEG-DASH Layers Packaging as well as manifest and MPD file generation
- Wide range of ingest codecs and formats

### Presets:

- DASH-264
- DASH-265

## 2. Installation

Before installing MainConcept 2GO, please ensure Docker is installed correctly.

### 2.1 Installing Docker

To download and install Docker on your server, please follow the instructions here: [www.docker.com/community-edition](http://www.docker.com/community-edition)

After successful installation you should be able to run the Docker "hello-world" container. Example output from the Docker hello-world container:

```
$ docker run hello-world

Hello from Docker!
This message shows that your installation appears to be working correctly.

To generate this message, Docker took the following steps:
1. The Docker client contacted the Docker daemon.
2. The Docker daemon pulled the "hello-world" image from the Docker Hub. (amd64)
3. The Docker daemon created a new container from that image which runs the executable that produces the output you are currently reading.
4. The Docker daemon streamed that output to the Docker client, which sent it to your terminal.
```

If you see different output, please refer to the Docker installation guide.



## 2.2 Resources for Docker

On Windows machines there is a default limitation of resources available for Docker. It could be adjusted in the "Settings > Advanced" section. For more information, please check the official website: [docs.docker.com/docker-for-windows](https://docs.docker.com/docker-for-windows).

## 2.3 Installing MainConcept 2GO

### 1) Extract the MainConcept 2GO package

To install your MainConcept 2GO product, first unpack the ZIP file you downloaded into a new folder on your computer. The files within the folder depend on the 2GO product.

```
total 40
drwxrwxr-x 2 thomas thomas 4096 Apr 10 14:23 docker
-rw-rw-r-- 1 thomas thomas 17835 Apr 10 14:23 EULA.txt
-rw-rw-r-- 1 thomas thomas 77 Apr 10 14:23 info.txt
-rw-rw-r-- 1 thomas thomas 2721 Apr 10 14:23 readme.txt
-rw-rw-r-- 1 thomas thomas 4096 Apr 10 14:23 scripts
-rw-rw-r-- 1 thomas thomas 4096 Apr 10 15:10 volume
~/MainConcept/2GO/mc_2go_mc_2go_ott_file_transcoder_dash_demo# █
```

### 2) Install the MainConcept 2GO docker image

To install the MainConcept 2GO image in your local Docker environment, "cd" into the docker folder and run the "install\_image" script:

```
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo# cd docker/
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/docker# ./install_image.sh
Installing MainConcept 2GO in your local Docker environment...
e6bc3d95b8d4: Loading layer [=====>] 28.87MB/28.87MB
Loaded image: mc_2go_ott_file_transcoder_dash_demo:latest
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo# █
```

Verify whether the 2GO container is installed properly by using the "docker image ls" command:

```
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/docker# docker image ls
REPOSITORY                                TAG          IMAGE ID      CREATED       SIZE
mc_2go_ott_file_transcoder_dash_demo     latest      2e15d1d96bd9 3 hours ago  39.9MB
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/docker# █
```



#### NOTE:

For using both the demo and full version of MainConcept 2GO, you must allow the server running MC2GO a connection to <https://taas-reporting-srv.mainconcept.com>.

If you want to use the products offline (i.e. without internet connection), please contact [customer.care@mainconcept.com](mailto:customer.care@mainconcept.com). We will get in touch with you about the necessary steps.



### 3. Settings

#### 3.1 Supported Input Codecs & Formats

MainConcept 2GO OTT File Transcoder DASH supports the following input codecs and formats:

- **Video:** MPEG-1/2, MPEG-4 Part 2, H.263, VC-1, HEVC/H.265, AVC/H.264, DV / DVCPRO, JPEG 2000, Apple ProRes, DNxHD, DNxHR
- **Audio:** PCM / LPCM, MPEG Layer 1/2/3, AAC / HE-AAC, WMA, AMR, RAW / WAV, DV, AC-3, E-AC-3
- **Container:** Elementary Streams, MPEG-2 Program Stream / Transport Stream, MP4, 3GP, F4V, ASF, DV, DIF, MJ2, MXF, RAW, MOV

#### 3.2 Supported Output Formats

MainConcept 2GO OTT File Transcoder DASH has support for the following output formats.

- DASH-264 (AVC/H.264 (8-bit) video and AAC LC audio) including fMP4 packaging and MPD / manifest file generation
- DASH-265 (HEVC/H.265 (8-bit/10-bit) video and AAC LC audio) including fMP4 packaging and MPD / manifest file generation

### 4. Configuration

With Docker installed most of the MainConcept 2GO configuration is complete. However, some 2GO products require shared folders, or specific parameters at startup.

#### 4.1 Configuring shared folders

To read and write files located on the host computer, MainConcept 2GO uses shared volumes to access the filesystem of the host. Docker uses mounted volumes to share host folders with 2GO containers.

The “run” convenience script in the scripts folder runs the MainConcept 2GO container and automatically maps the required folders from your host computer into the 2GO container.



### 4.2 Preset Usage

DASH-264 4K 16x9.mps:

MC2GO Value	Video Settings	Audio Settings
v1	Layer 1: AVC/H.264, 8-bit, 768x432, 400 kb, 16x9	
v2	Layer 2: AVC/H.264, 8-bit, 768x432, 600 kb, 16x9	
v3	Layer 3: AVC/H.264, 8-bit, 768x432, 800 kb, 16x9	
v4	Layer 4: AVC/H.264, 8-bit, 768x432, 1200 kb, 16x9	
v5	Layer 5: AVC/H.264, 8-bit, 1280x720, 1750 kb, 16x9	
v6	Layer 6: AVC/H.264, 8-bit, 1280x720, 2400 kb, 16x9	
v7	Layer 7: AVC/H.264, 8-bit, 1920x1080, 3500 kb, 16x9	
v8	Layer 8: AVC/H.264, 8-bit, 1920x1080, 5300 kb, 16x9	
v9	Layer 9: AVC/H.264, 8-bit, 1920x1080, 8400 kb, 16x9	
v10	Layer 10: AVC/H.264, 8-bit, 3840x2160, 15000 kb, 16x9	
v11	Layer 11: AVC/H.264, 8-bit, 3840x2160, 20000 kb, 16x9	
v12	Layer 12: AVC/H.264, 8-bit, 3840x2160, 25000 kb, 16x9	
a1		Layer 1: AAC-HEV1, stereo, 32 kbps, 48 khz, 16-bit
a2		Layer 2: AAC-HEV1, stereo, 96 kbps, 48 khz, 16-bit
a3		Layer 3: AAC-LC, stereo, 96 kbps, 48 khz, 16-bit
a4		Layer 4: AAC-LC, stereo, 160 kbps, 48 khz, 16-bit
a5		Layer 5: AAC-HEV1, 5.1 ch, 128 kbps, 48 khz, 16-bit
a6		Layer 6: AAC-HEV1, 5.1 ch, 256 kbps, 48 khz, 16-bit

DASH-265 4K 16x9.mps:

MC2GO Value	Video Settings	Audio Settings
v1	Layer 1: HEVC/H.265, 8-bit, 768x432, 400 kb, 16x9	
v2	Layer 2: HEVC/H.265, 768x432, 600 kb, 16x9	
v3	Layer 3: HEVC/H.265, 8-bit, 1280x720, 900 kb, 16x9	



# MainConcept 2GO OTT File Transcoder DASH

## User Guide

v4	Layer 4: HEVC/H.265, 8-bit, 1280x720, 1400 kb, 16x9	
v5	Layer 5: HEVC/H.265, 8-bit, 1280x720, 2100 kb, 16x9	
v6	Layer 6: HEVC/H.265, 8-bit, 1920x1080, 3100 kb, 16x9	
v7	Layer 7: HEVC/H.265, 8-bit, 1920x1080, 5000 kb, 16x9	
v8	Layer 8: HEVC/H.265, 8-bit, 1920x1080, 7500 kb, 16x9	
v9	Layer 9: HEVC/H.265, 8-bit, 3840x2160, 10000 kb, 16x9	
v10	Layer 10: HEVC/H.265, 8-bit, 3840x2160, 15000 kb, 16x9	
a1		Layer 1: AAC-HEV1, stereo, 32 kbps, 48 khz, 16-bit
a2		Layer 2: AAC-HEV1, stereo, 96 kbps, 48 khz, 16-bit
a3		Layer 3: AAC-LC, stereo, 96 kbps, 48 khz, 16-bit
a4		Layer 4: AAC-LC, stereo, 160 kbps, 48 khz, 16-bit
a5		Layer 5: AAC-HEV1, 5.1 ch, 128 kbps, 48 khz, 16-bit

DASH-265 Main 10 4K 16x9.mps:

MC2GO Value	Video Settings	Audio Settings
v1	Layer 1: HEVC/H.265, 10-bit, 768x432, 600 kb, 16x9	
v2	Layer 2: HEVC/H.265, 10-bit, 1280x720, 5000 kb, 16x9	
v3	Layer 3: HEVC/H.265, 10-bit, 1920x1080, 7500 kb, 16x9	
v4	Layer 4: HEVC/H.265, 10-bit, 3840x2160, 15000 kb, 16x9	
a1		Layer 1: AAC-HEV1, stereo, 32 kbps, 48 khz, 16-bit
a2		Layer 2: AAC-HEV1, stereo, 96 kbps, 48 khz, 16-bit
a3		Layer 3: AAC-LC, stereo, 96 kbps, 48 khz, 16-bit
a4		Layer 4: AAC-LC, stereo, 160 kbps, 48 khz, 16-bit
a5		Layer 5: AAC-HEV1, 5.1 ch, 128 kbps, 48 khz, 16-bit



## 5. Usage

### 5.1 Starting MainConcept 2GO

Make sure you have successfully installed your MainConcept 2GO product on the computer by following the Installation instructions.

The “run” script inside the scripts folder makes starting MainConcept 2GO easy and lets you understand how 2GO docker containers are actually run. If you plan to run MainConcept 2GO through container management tools like Docker Compose, Kubernetes or Docker Swarm, it is recommended that you understand the parameters required for 2GO containers by reading the “run” script.

MainConcept 2GO products require passing configuration parameters to the container at startup. These can include input and output filenames, serial keys, shared volume folders or external URLs. These parameters can be specified in a properties file or via the command line.

### 5.2 Using job description file

MainConcept 2GO v2.0 introduces a REST API and provides users an interface that is more suitable for integration with their existing environment or tools. This API covers functionality to create jobs and query their status using standard REST API calls over HTTP. A job description file is posted to the endpoint, which must be in JSON format. This JSON file must contain all necessary parameters required for the submitted jobs.

Option	Sample value	Description
INPUT		Source filename for audio conversion; must be in or under SHARED_PATH_IN
OUTPUT	test.mp4	Target filename for encoded output; the file extension will be created by 2GO; must be in or under SHARED_PATH_OUT  File Extension: *.mp4
PRESETNAME	DASH-264 4K 16x9	Preset name for MPEG-DASH generation when using original MainConcept preset(s) included with the Docker container. Note: When PRESETNAME is used, PRESET must not be used.
PRESET	<folder_in_shared_path>/dash264/DASH-264 4K 16x9.mps	Custom preset file(s) (MPS); must be in or under SHARED_PATH_IN volume outside of the Docker container. Note: When PRESET is used, PRESETNAME must not be used.



# MainConcept 2GO OTT File Transcoder DASH

## User Guide

VIDEO_LEVELS	v3,v5,v7,v8,v11	<ul style="list-style-type: none"> <li>Video levels / layers in the preset files</li> </ul>
AUDIO_LEVELS	a1,a3,a5	Audio levels / layers in the preset files.
VERBOSITY	SILENT	<p>Sets verbose level. Available options are:</p> <ul style="list-style-type: none"> <li>SILENT (0) - Prints only error messages</li> <li>DEFAULT (1) - Default level if verbose level is not specified. Prints information about input file, output file, preset. Prints information about REST API calls (target URLs with parameters, no BODY info).</li> <li>FULL (2) - Prints all available information, including processing status, file transfer, REST API calls (target URLs with parameters with BODY info), complete information from processing step.</li> </ul>
KEEP_CONTENT	TRUE	Prevents deletion of temporary content (e.g. downloaded, transcoded). Default value is FALSE.
TRIM_IN	3.330s	In point in seconds (e.g. 3.330s) or in frames (e.g. 250f). Regarded as the start point if specified.
TRIM_OUT	250f	Out point in seconds (e.g. 3.330s) or in frames (e.g. 250f). Regarded as the end point if specified.
LOGO_PATH		<p>Path to the file. Overlays PNG image onto video stream.</p> <p>Note: Path to local file should be relative to SHARED_PATH_IN.</p>
LOGO_OFFSET_LEFT	123	Horizontal offset from left-top corner of the frame in pixels.
LOGO_OFFSET_TOP	45	Vertical offset from left-top corner of the frame in pixels.
LOGO_BEGIN_TIME	3.330s	The time from which the logo appears in seconds (e.g. 3.330s).
LOGO_END_TIME	8.330s	The time from which the logo disappears in seconds (e.g. 8.330s).





To edit the parameters of the JSON file, use a text editor. Here are some examples:

```
{
  "INPUT": "ftp://10.144.41.202:2121/test.mp4",
  "OUTPUT": "ftp://10.144.41.202:2121/test/123AB0CD",
  "PRESETNAME": "DASH-264 4K 16x9",
  "VIDEO_LEVELS": "v3-avc,v5-avc,v7-avc",
  "AUDIO_LEVELS": "a1",
  "KEEP_CONTENT": "TRUE",
  "VERBOSEITY": "FULL"
}

{
  "INPUT": "/volume/test.mp4",
  "OUTPUT": "/volume_out/123AB0CD",
  "PRESET": "DASH-264 4K 16x9",
  "VIDEO_LEVELS": "v3-avc,v5-avc,v7-avc",
  "AUDIO_LEVELS": "a1",
  "KEEP_CONTENT": "TRUE",
  "VERBOSEITY": "FULL"
}
```

### 5.3 Using properties file

The easiest way to start MainConcept 2GO is by editing the “properties.txt” file to your needs and then executing the “run” script with this file.

```
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo# ./scripts/run.sh
scripts/properties.txt
```

The MainConcept 2GO OTT File Transcoder DASH supports the following configuration options:

Option	Sample value	Description
ACCEPT_EULA	YES	Required
CUSTOMER_ID		User's unique identifier, provided by MainConcept after purchase. Customer ID parameter can also be specified more concisely as `CID`
SHARED_PATH_IN	/path/source_folder	Optional: Folder where the input file is located
SHARED_PATH_OUT	/path/target_folder	Optional: Folder for the encoded output file
JOBS	/path/to/json_file	Optional: Specify a job JSON file for immediate processing
PORT	8082	Specify port for REST API. Default value is 8080.
AUTOSTART	TRUE, FALSE	Disable/enable job queue processing when Docker runs. FALSE sets the service to a



# MainConcept 2GO OTT File Transcoder DASH

## User Guide

		stopped state after the Docker runs. Default value is TRUE.
VERBOSITY	SILENT	Sets verbose level. Available options are: - SILENT (0) - Prints only error messages - DEFAULT (1) - Default level if verbose level is not specified. Prints out the copyright/version information - FULL (2) - Higher verbose level. Prints all available information including command-line parameters INPUT / OUTPUT / PRESETS / SERIAL
TRIM_IN	3.330s	In point in seconds (e.g. 3.330s) or in frames (e.g. 250f). Regarded as the start point if specified.
TRIM_OUT	250f	Out point in seconds (e.g. 3.330s) or in frames (e.g. 250f). Regarded as the end point if specified.
LOGO_PATH		Path to the file. Overlays PNG image onto video stream.  Note: Path to local file should be relative to SHARED_PATH_IN.
LOGO_OFFSET_LEFT	123	Horizontal offset from left-top corner of the frame in pixels.
LOGO_OFFSET_TOP	45	Vertical offset from left-top corner of the frame in pixels.
LOGO_BEGIN_TIME	3.330s	The time from which the logo appears in seconds (e.g. 3.330s).
LOGO_END_TIME	8.330s	The time from which the logo disappears in seconds (e.g. 8.330s).

To edit the parameters, use a text editor:

```
1 ACCEPT_EULA=Y
2 SHARED_PATH_IN=~/.MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/volume
3 SHARED_PATH_OUT=~/.MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/volume
4 JOBS=~/.path/to/json_file
5 PORT=8082
6 AUTOSTART=TRUE
7 CUSTOMER_ID=xxx
8 VERBOSITY=DEFAULT
```



### Using command line options

Instead of editing a properties file, all configuration parameters can also be specified on the command line directly.

```
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/docker# ./scripts/run.sh \  
> ACCEPT_EULA=Y \  
> SHARED_PATH_IN=~/.MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/volume \  
> SHARED_PATH_OUT=~/.MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/volume \  
> JOBS=~/.path/to/json_file \  
> PORT=8082 \  
> AUTOSTART=TRUE \  
> CUSTOMER_ID= xxx \  
> VERBOSITY=DEFAULT
```

### Using docker-compose

Docker Compose lets you start multiple replicas of the same image. It also significantly simplifies starting MainConcept 2GO products.

Docker Compose is a separate tool that must be installed in addition to Docker. Please refer to the documentation about how to install and setup Compose: [docs.docker.com/compose/](https://docs.docker.com/compose/)

To run MainConcept 2GO with Docker Compose you create a compose file in YAML. All parameters to run the 2GO product via Docker Compose are specified inside this YAML file. To simplify deployment of MainConcept 2GO containers, setting environment variables for the 2GO configuration and then using them in the YAML file is recommended.

This is a basic "docker-compose.yml" file showing how to configure MainConcept 2GO.

```
1 version: '2.2'  
2 services:  
3   2go:  
4     image: 2go_ott_file_transcoder_dash_demo  
5     network_mode: host  
6     volumes:  
7       - ${2GO_VOLUME}:/volume  
8     environment:  
9       - 2GO_PARAMS=${2GO_PARAMS}
```

It uses two environment variables 2GO\_VOLUME and 2GO\_PARAMS. These must be set before starting docker-compose.

```
~# export 2GO_VOLUME=~/.MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo/volume/  
~# export 2GO_PARAMS="INPUT=avchd_camera_testfile.mts OUTPUT=out_file  
PRESET=presets/DASH-265_4K_16x9.mps SERIAL=serials.txt"
```

After that starting 2GO using Docker Compose is as easy as:

```
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo# docker-compose up -d  
Starting mc2goottfiletranscoderdashdemo_2go_1 ...  
Starting mc2goottfiletranscoderdashdemo_2go_1 ... done  
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo#
```



## 5.5 Stopping MainConcept 2GO execution

MainConcept 2GO containers should be stopped using the convenience “stop” script provided in the scripts folder.

To execute the script on an active container you first need to know the container ID. This can be found from the first column of the docker ps command:

```
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo# docker ps
CONTAINER ID IMAGE COMMAND CREATED
bc45686deb0e mc_2go_ott_file_transcoder_dash_demo "/opt/bin/reporting_..." 4seconds ago
```

Then use the convenience “stop” script in the scripts folder to abort the 2GO execution:

```
~/MainConcept/2GO/mc_2go_ott_file_transcoder_dash_demo# ./scripts/stop.sh bc45686deb0e
Stopping the OTT File Transcoder DASH...
OTT File Transcoder DASH stopped.
~/MainConcept/2GO/mc_2go_ott_file_transcoder_hls_demo# █
```

If you are using the REST API, you also have the opportunity to shut down the container by using DELETE /service. If a job is currently active, the container is not shut down and this function is ignored. In this case you need to abort the job first using POST /jobs/{jobID}/abort

## 6. Technical Support

If you need additional assistance, the MainConcept Technical Support team is standing by to help. Send an e-mail to [apps.support@mainconcept.com](mailto:apps.support@mainconcept.com) or go to the [MainConcept Support page](#) and we'll assist you as quickly as possible.



## 7. Credits

Copyright © 2021 MainConcept GmbH or its affiliates. All rights reserved.



MainConcept® and its logos are registered trademarks of MainConcept GmbH or its affiliates. This software is protected by copyright law and international treaties. Unauthorized reproduction or distribution of any portion is prohibited by law.

This manual, as well as the software described in it, is furnished under license and may only be used or copied in accordance with the terms of such license. The information in this manual is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment or representation by MainConcept GmbH or its affiliates. MainConcept GmbH and its affiliates assumes no responsibility or liability for any errors or inaccuracies that may appear in this book and use is at your sole risk.

Except as permitted by such license, no part of the publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of MainConcept GmbH.

Docker and the Docker logo are trademarks or registered trademarks of Docker, Inc. in the United States and/or other countries. Docker, Inc. and other parties may also have trademark rights in other terms used herein. Copyright 2018 Docker, Inc. All rights reserved.

Adobe and Flash are trademarks or registered trademarks of Adobe Systems Incorporated in the USA and other countries.

DTS, the Symbol, and DTS-HD are registered trademarks of DTS, Inc.

Dolby Digital codec manufactured under license from Dolby Laboratories. Dolby and the double-D symbol are trademarks of Dolby Laboratories. Unpublished work. Copyright 2003-2014 Dolby Laboratories, Inc. and Dolby Laboratories Licensing Corporation. All rights reserved.

AAC's HE-AAC and HE-AAC v2 versions are regarded as today's most efficient general perceptual audio codecs. AAC has been standardized by ISO and IEC as part of the MPEG specifications. It is understood that it may be necessary to execute a patent license with the appropriate AAC licensing entities in order to obtain all rights necessary to create and exploit products utilizing AAC and it is recommended to contact the appropriate licensing entities, e.g. Via Licensing ([www.vialicensing.com](http://www.vialicensing.com)), and negotiate in good faith the adequate contracts, if any.

Fraunhofer Institute for Integrated Circuits IIS  
Attention: Audio and Multimedia Departments - MC AAC LL  
Am Wolfsmantel 33, 91058 Erlangen, Germany  
[www.iis.fraunhofer.de/amm](http://www.iis.fraunhofer.de/amm)  
[amm-info@iis.fraunhofer.de](mailto:amm-info@iis.fraunhofer.de)

Microsoft, Microsoft Windows XP, Windows Media Player, and the Microsoft logo are registered trademarks of the Microsoft Corporation, Inc.

All other company or product names are trademarks or registered trademarks of their respective owners.

MC2GO Product Version: 2.3

Last User Guide Update: June 14, 2021

